



LEARN & CREATE

with Baby Lock

Updating Your Baby Lock Valiant with IQ Designer


If your Baby Lock Valiant did not come with IQ Designer built into your machine, get the free update over at <http://babylock.com/downloads/> and follow this video to learn how to update your Valiant to enable its IQ Designer capabilities!

Table of Contents

Do You Need this Update?	1
Get the Free Update	2
Install the Update in the Valiant	4
Unlock the IQ Update	6


Do You Need this Update?

1. If your Valiant came without the IQ Designer already loaded in the machine, this video will show you how to download and install the update to add IQ Designer to your Valiant
2. If you already have IQ Designer loaded in your Valiant, you will have an IQ icon  in the lower right corner of the LCD screen like the machine shown at the right in the image below
3. If you do not have an IQ icon , like the machine at the left in the picture, then you will want to watch this video to see how to add IQ to your Valiant




Get the Free Update


1. Go to the Baby Lock website at www.Babylock.com
2. Left click Support at the top right of the page



3. On the Support page, scroll down and select Machine Support



4. On the Machine Support page, scroll down to find the Multi Needle Embroidery category






5. Select Get Downloads for the Valiant
6. Click Download

V. 1.21 UPDATE VALIANT (BMV10)

Added: 09/20/2017



7. A tab appears in the lower left corner of the computer screen showing that the file is downloading




When the file finishes downloading:

1. You need to find where the file has been saved in your computer
2. The easiest way to do that is to left click the arrow




3. A menu opens of things you can do with the download and one of those is "Show in Folder"




4. Left click Show in Folder and your Computer File list opens with the newly downloaded file highlighted





5. Place a USB flash drive in the computer
 - Use a formatted flash drive with no other files on it.
 - To format a flash drive, right click on the drive in the file list and select Format
6. Click and drag to move the highlighted update file to the flash drive
7. If you left click to select the flash drive in the file list, you should see only the update file on that drive



Install the Update in the Valiant

1. Take the USB flash drive out of the computer and bring it over to the machine
2. Turn the Valiant OFF



3. Hold the Needle Threading Button while you turn the Valiant back on
4. The Valiant displays a screen with three different icons.



- The icon you select tells the machine where to look for the download file
5. Place the USB flash drive in the USB port on the Valiant
 6. Select the USB icon  on the left




7. A new screen is displayed which tells you to “Press Load after connecting the USB media containing the upgrade file.”



8. You have already done that, so simply touch



9. And now you wait which the file is installed in your Baby Lock Valiant



- When the update has been installed, the LCD screen displays a message that says "Upgrade complete"




- Turn the Valiant OFF
- And then turn the Valiant back ON

Unlock the IQ Update

- Place the scanning frame on the Valiant



- Once the scanning frame has been attached to the carriage and recognized by the Valiant, the IQ icon  will appear in the lower right corner of your LCD screen.



3. Note that for the update to be recognized, the scan hoop just had to make contact with the hoop sensor
4. But if you are going to be scanning, please use the hoop screws and attach the frame securely

